

Simple Text Rotator Plugin v.1.1 4 min read

Thank You For Purchasing Simple Text Rotator Plugin!

You can read below a comprehensive guide with detailed instructions about the Simple Text Rotator Plugin functionalities. Each section is carefully explained, using helpful screenshots when necessary. It contains everything you need to have your plugin up and running in no time.

[Online Documentation](#)

1. Table of Contents

[Free Support](#)

[Install the Plugin](#)

[Shortcode Usage](#)

[Release Notes](#)

2. Free Support


We provide **Free Customer Support for all Curly Themes** products through our quick and easy ticket application interface. Please limit your inquiries to problems related to the plugin, its setup and features. For any problems concerning third-party plugins you should address the application's developer.

Note: We can not offer support for custom CSS code customization. You should ask a professional developer for aid if you require help with advanced customization and programming.

Free Ticket Support

Curly Themes offers a **free ticket support application** for all clients, through a real-time purchase code automatic verification. The dedicated app is **fast and easy to use** and includes an email notification feature. We will let you know as soon as your inquiry has received an answer. Thanks to our modern design, you can also upload images as an attachment to your support ticket.

Before writing a ticket please get your License Certificate:



❗ Simple Text Rotator

Before **opening a new ticket**, please make sure you have read through **all our documentation**. Also, our **Knowledge Base** [↗](#) contains helpful answers to questions we often receive from our customers. Following these steps is in the users' interest, as they will save valuable time. Still, we are always happy to respond to any inquiries you may have related to our theme.

Create Support Ticket Knowledge Base

3. Install the Plugin

Before installing this plugin you need to have a **WordPress** platform already **installed on your server**. You can download it from **WordPress.org** [↗](#) if you don't have it already.

If you do not know how or you have problems with the installation, you can access helpful information at:

- **WordPress Codex** [↗](#)
- **WP101 Training Video** [↗](#)

- [WordPress FAQ](#) 

Once you have a working WordPress on your server, you have two available ways to install this plugin.

3.1. FTP Upload

The **.zip** file you downloaded from Theme Forest contains a folder named **simple-text-rotator**. Upload this folder on your server in your WordPress directory to **/wp-content/plugins/**


3.2. WordPress Upload

The second way to install the plugin is by logging in from your website **/wp-admin** to the **WordPress Dashboard**. From there, you should go to **Appearance > Plugins > Add New > Upload** and select the file **simple-text-rotator.zip** from your computer. After clicking the **Install Now** button, the installation process is finished.

3.3. Activating the Simple Text Rotator Plugin

After you have completed the install process, in either of the two ways, you need to activate it. Log in to the **WordPress Dashboard**, go to **Plugins > Installed Plugins** and select **Simple Text Rotator Plugin**. Click the **Activate** button and you can start using the plugin.

4. Shortcode Usage

The plugin has two available shortcodes: one for rotating normal text (no links, bold, etc) and one for rotating blocks of content (links, bold, images, etc). The plugin is powered by [animate.css](#)  animations.

4.1. Simple Text Rotator

```
[simple-text-rotator animation="fadeIn" separator="|" speed="2000"] cool | simple | nice [/simple-text-rotator]
```

Parameters:

- **animation** – Available animations are: bounce, flash, pulse, rubberBand, shake, swing, tada, wobble, bounceIn, bounceInDown, bounceInLeft, bounceInRight, bounceInUp, fadeIn, fadeInDown, fadeInDownBig, fadeInLeft, fadeInLeftBig, fadeInRight, fadeInRightBig, fadeInUp, fadeInUpBig, flip, flipInX, flipInY, lightSpeedIn, rotateIn, rotateInDownLeft, rotateInDownRight, rotateInUpLeft, rotateInUpRight, rollIn, zoomIn, zoomInDown, zoomInRight, zoomInUp, zoomInLeft
- **separator** – Choose a character as separator. Any character is allowed. Default is: “|”
- **speed** – Choose the animation speed in milliseconds. Default is: 2000

4.2. Simple Content Rotator

```
[simple-content-rotator animation="fadeIn" animation_out="bounceOut" speed="2000"]
```

Sample Paragraph

Another Text

```
[/simple-content-rotator]
```

Parameters:

- **animation** – Available animations are: bounce, flash, pulse, rubberBand, shake, swing, tada, wobble, bounceIn, bounceInDown, bounceInLeft, bounceInRight, bounceInUp,

fadeIn, fadeInDown, fadeInDownBig, fadeInLeft, fadeInLeftBig, fadeInRight, fadeInRightBig, fadeInUp, fadeInUpBig, flip, flipInX, flipInY, lightSpeedIn, rotateIn, rotateInDownLeft, rotateInDownRight, rotateInUpLeft, rotateInUpRight, rollIn, zoomIn, zoomInDown, zoomInRight, zoomInUp, zoomInLeft

- **animation_out** – Available animations are: bounceOut, bounceOutDown, bounceOutLeft, bounceOutRight, bounceOutUp, fadeOut, fadeOutUp, fadeOutUpBig, fadeOutRight, fadeOutRightBig, fadeOutLeft, fadeOutLeftBig, flipOutX, flipOutY, lightSpeedOut, rotateOut, rotateOutDownLeft, rotateOutDownRight, rotateOutUpLeft, rotateOutUpRight, rollOut, zoomOut, zoomOutDown, zoomOutLeft, zoomOutRight, zoomOutUp
- **speed** – Choose the animation speed in milliseconds. Default is: 2000

5. Release Notes:

Simple Text Rotator Plugin 1.1. (January 18, 2014)

Last Documentation Update: Monday, February 22, 2016